
Langkah – langkah upload:


1 Buka aplikasi SR14+ABC Firmware Update Ver2.0. (*terlebih dahulu harus install .NET Framework 3.5).



- 2 Atur COM Port, lalu pilih dan pastikan Port nya tersedia.
- **3** Atur Baud ke 115200.
- 4 Atur Select Board Type jadi DualMCU.
- 5 Lalu klik Open. Lalu, tunggu sampai ada notifikasi opened di kiri bawah pojok.




6 Centang APP Processor Firmware saja. Lalu klik Browse



7 Klik file AppProcessorApplicaiton.bin, lalu klik Open

Start Firmware Update

8 Klik Start Firmware Update, dan tunggu hingga selesai.



9 Jika, berhasil dan sukses. Maka tampilannya akan sepert ini.

